

At AAON, we are committed to continuously enhancing our products through regular software updates. The release notes below provide an overview of updates, features, and hot fixes introduced in the most recent software versions. This document may not include all changes, especially minor adjustments or security enhancements. Features may vary depending on user settings or environment.

Note: AAON software updates are rolled out in phases to monitor performance and adjust as needed before being available to all users. If you are unable to update your software but see new release notes, please check back soon for future availability. It is the responsibility of the building manager to ensure all devices remain current with the latest compatible software version.

| | |
|---|-------------------|
| Chiller Pumping Module SS1130 Software release notes | |
| Software version 1.06 – Current Version <ul style="list-style-type: none">• New feature:<ul style="list-style-type: none">○ Added a “Pump Runtime” menu and “Reset Runtime” option in the hidden menu.• Improvements<ul style="list-style-type: none">○ Added a live lead/lag changeover configuration to the change pumps (both main and backup) while running.○ Removed the missing HXC glycol-side outlet sensor alarm, as not all configurations use it. For configurations that do include an HXC glycol-side outlet sensor, the sensor helps prevent freezing. | November 02, 2020 |